Using Dealmaster Pro with PlayBridge Dealer4

Pete Matthews, March 19, 2008; minor updates July 3, 2009

Required Software

Obtain and install:

- 1. The Dealer4 software that came with your PlayBridge Dealer4.
- 2. Dealmaster Pro, \$60 from Ward Software, http://www.dealmaster.com/.
- 3. CutePDF Writer, free from http://www.cutepdf.com/.
- 4. Adobe Acrobat Reader, free from http://www.adobe.com/.

Primary File Formats

Four file formats are handled by both Dealmaster Pro and the PlayBridge Dealer4 software:

- .BRI Dealer4, Autodealer, and BridgePartner (the Dealer4 default)
- .BRE Autodealer
- .DUP Duplimate (older DOS format, good for ACBL-generated deals, works with ScoreBridge)
- .PBN Portable Bridge Notation (includes GIB)

Other formats: Dealmaster Pro will also "Import" these other formats: .DLM (Duplimate for Windows), .CDS, .LIN (Bridgebase), and an exported Dealmaster Profile. You can create files in various formats from DM Pro, by checking the "Create Files for..." box (instead of Print North...) - see "Create the Hand Records" below. Any file that can be loaded into Dealer4 can be saved in the formats above.

Dealer4 Setup




One time only, start the **Dealer4** software and click **Setup** on the Dealer4 main menu (see "Deal the Cards").

- Select one of the four primary deal types (any here except .dge), and
- b. click Save.

Choose any **one primary file format**, and try to stick to it. Choose the format that is most likely to be used by your bridge organization. I used .dup for a year, but now use .pbn – I may use it with a free program called <u>ACBLmerge</u>.

Dealmaster Pro Setup

Miscellaneous Functions Menu



One time only, start the **Dealmaster Pro** software (see "Generating Random Deals"), and click **Miscellaneous** on the main menu.

Then, in turn, click


- a. My Name and Preferences,
- b. Language Selection, and
- c. Misc. Problems/Other

Setup and Preferences
My Name and Preferences
You may change the following at any time. See Miscellaneous Menu option.
Enter title to appear at top of printouts normally your name or name of your club:
My Name: MIT/DL Bridge Club
☑ Fill 4th hand when three hands are filled.
Hollow Heart and Diamond symbols for Word Perfect
Position arrow at spade row when hand is full.
Unused F
☑ Deal Detail printouts: show suit symbols for hands not selected
ок

Enter the name of your bridge club as My Name, and click OK.

Language Selection The selection of a language and	Enter the correct word in your language for the English word:			
	English word: English "North" "East" "South" "West" "Deal (Hand) No." "Dealer" "Neither Vulnerable" "N-S Vulnerable" "E-W Vulnerable" "Both Vulnerable" "Opening Lead" "All Hands"	Your Language North East South West Deal No. Dealer 'Neither Vulnerable N-S Vulnerable E-W Vulnerable Both Vulnerable Opening Lead All Hands		
	"Illustrates" "All Pass" "Pass" "Double" "Redouble" "NT" "Board No." "Contract" "By" AKQJT (Honor cards)	Illustrates All Pass Pass Db1 RedD1 NT Board No. Contract By AKQJT		

Select your **Language**. If not English (USA), you may need to enter the information on the right. Click **OK** when done.



Be sure that **DMPRO font now active** is displayed. If not, click **Deactivate/Activate DMPRO font**, and then **Exit**.

Generate Random Deals into a Deal File

Skip this section, if you already have a deal file in one of the four primary file formats.

The Dealer4 software may generate random deals, but you really need other software for that, such as Dealmaster Pro. This powerful program has a quirky interface, but ultimately it will produce top quality hand records, including analysis by Deep Finesse. (If you teach bridge, you should appreciate the ability to create a library of categorized hands for lessons, but that's beyond the scope of this article.) For our purposes, the best thing to do is to limit use of DM Pro to the distinct operations required. To generate the deals for one session:



1. Start Dealmaster Pro.



2. Click the first option on the main menu: Create random deals for club/tournament play.

Create Random Deals

Help file topic "Big Deal" has extensive information about Big Deal and under what circumstances it is adviseable to use it. Generally, it is preferable for generating deals for tournament use where the deal generator must be capable of generating all of the 53,000,000,000,000,000,000,000,000+ possible deals. Big Deal can do this. Dealmaster Pro can generate slightly fewer.

There are many more output options for deals generated by Dealmaster Pro. All the options for deals generated by Big Deal are given below.

• 1. Use Dealmaster Pro deal generator

• 2. Use Big Deal deal generator.

Print Hand Record Output File options: PBN (Portable Bridge Notation) file Duplimate DLM file Duplimate DUP file Autodealer BRI file	Number of deals: 36 (Max: 50000) Print Hand Record Output File options: PBN (Portable Bridge Notation) file Duplimate DLM file Autodealer BRI file Autodealer BRE file	Session: Name: anyname
 Print Hand Record Output File options: PBN (Portable Bridge Notation) file Duplimate DLM file Duplimate DUP file Autodealer BRI file Autodealer BRE file 	 Print Hand Record Output File options: PBN (Portable Bridge Notation) file Duplimate DLM file Duplimate DUP file Autodealer BRI file Autodealer BRE file 	Date: 04/01/2008
Output File options: C PBN (Portable Bridge Notation) file Duplimate DLM file Duplimate DUP file C Autodealer BRI file Autodealer BRE file	Output File options: OPBN (Portable Bridge Notation) file Duplimate DLM file Duplimate DUP file Autodealer BRI file Autodealer BRE file	Number of deals: 36 🗧 (Max: 50000)
 PBN (Portable Bridge Notation) file Duplimate DLM file Duplimate DUP file Autodealer BRI file Autodealer BRE file 	 PBN (Portable Bridge Notation) file Duplimate DLM file Duplimate DUP file Autodealer BRI file Autodealer BRE file 	🗖 Print Hand Record
C Duplimate DLM file Duplimate DUP file Autodealer BRI file Autodealer BRE file	C Duplimate DLM file C Duplimate DUP file C Autodealer BRI file C Autodealer BRE file	Output File options:
C Duplimate DUP file C Autodealer BRI file C Autodealer BRE file	C Duplimate DUP file C Autodealer BRI file C Autodealer BRE file	O PBN (Portable Bridge Notation) file
C Autodealer BRI file C Autodealer BRE file	C Autodealer BRI file C Autodealer BRE file	C Duplimate DLM file
C Autodealer BRE file	O Autodealer BRE file	Duplimate DUP file
		C Autodealer BRI file
Save Hand Becord and File option as default	Save Hand Record and File option as defaults	O Autodealer BRE file
		Save Hand Record and File option as defaults

- 3. Select 2. Use Big Deal deal generator, and then:
 - a. Enter **any name** (won't be saved in the deal file)
 - b. Specify the date of the game
 - c. Enter the number of deals (likely 36 or 32)
 - d. Do *not* check Print Hand Record
 - e. Select one of the four primary file formats (e.g. Duplimate DUP file)
 - f. Check Save Hand Record and File option as defaults
 - g. Click OK



4. Click **NO**, do not show a statistical summary.

Save in: 🗀 dmpro 🔽 🗢 🛍) 📸 🎟 -
ianguages ∰ 080325.DUP	
Name of DUP 080401	Save
Save as type: dup	Cancel
	Help
	Code Page


- 5. Save the deal file:
 - a. Name the deal file. For use with ACBLscore,**YYMMDD** or YYMMDDs (where s is M, A, E or L) is appropriate 080401 is for April 1, 2008.
 - b. It's best to use the default DM Pro directory, C:\dmpro.
 - c. Click Save.

In subsequent steps, this deal file will be used to both create the hand records and deal the hands.

Create the Hand Records

Creating the hand records takes quite a bit of computer processing. You could do this in the step above, but you would not get the deal file until the very end. Separating the steps allows you to start the hand records, and deal the cards while waiting.

- 1. Start DM Pro, if not already started (see "Generating Random Deals").
- 2. Click the Miscellaneous option (see "Dealmaster Pro Setup" above).



3. Click Import Deal Files.

IMPORT FILE When the file you select is imported, you will have a variety of options to indicate what you want done with the deals in the imported file. Select the type of file to be imported: Dealmaster File C Dealmaster Pro File exported Bridge Playing Programs: C PBN file (including GIB) O * Q-Plus (English BDE) C * Q-Plus (French BDF) C * Q-Plus (German BDD) C * Microbridge (HND) O * Bridgemate O * Perfect Partner **Card Dealing Machines:** C Dealer4, Autodealer and BridgePartner (BRI) O Autodealer (BRE) Ouplimate (DUP) O Duplimate (DLM for Windows) C CDS file C LIN (BridgeBase) file * = Not yet operational OK

4. Select your **deal file type**, and click **OK**.

Look in: 🔀	dmpro	•	÷	£	ď	
🛅 languages 👬 080325.DU	P					
1080401.DU	P					
L				_	_	
Select	080401.DUP					Import file
Files of type:	*.dup			•		Cancel
						Help
					C	ode Page

- 5. Select the deal file, and click Import File
- 6. Click **OK**, if a blue informatory screen appears.

Out	put Options for selected/imported Deals 🔸 Cylion is create a lexible of the	
	ber of Selected Deals: 36 Enter Session Name: on(Select 1 or more) Session Date: 04/01/200	18
Α	Add selected deals to Browse File Classify selected deals	
в	Select Deal Printouts desired: 1 deal/page 2 deals/page 3 deals/page 4 deals/page	
с	Select any Hand Record printouts desired: ✓ Print North, South, East and West hands ✓ Print South only ✓ Print North and South hands only ✓ Print East and West hands only ✓ Print East and West hands only ✓ Print North only ✓ Print North only ✓ Print North only ✓ Print North only ✓ Print Date ✓ Color Choice: ✓ ◆ ♥ 	• • •
D	Format:	Across Across
E	📩 🗖 Print Goldway Practice Bid format(Used by Bobby GOLDman-Paul SoloWA	Y)
E		
	Create files for GIB, Q-Plus, Microbridge,BridgeMate,Perfect Partner; DUPLIMATE & AUTODE	ALER machines
G	Create files for GIB, Q-Plus, Microbridge,BridgeMate,Perfect Partner; DUPLIMATE & AUTODE Print Traveller with cards held by N,E,S and W	ALER machines
G On F	■ Print Traveller with cards held by N,E,S and W = Option to create output Text file Printouts, show Dealer and Vulnerability? © Yes ○ No	ALER machines
G On F	Print Traveller with cards held by N,E,S and W = Option to create output Text file Printouts, show Dealer and Vulnerability? G Xee, C Ne	se previous text
G On F	■ Print Traveller with cards held by N,E,S and W = Option to create output Text file Printouts, show Dealer and Vulnerability? © Yes ○ No	se previous text

- 7. Be sure to get this page right:
 - a. Leave the Session Name blank
 - b. Change the Session Date to the date of the game
 - c. Check Print North, South, East and West Hands





8. Click Yes, show makeable contracts on Hand Record.



9. Select More Comprehensive Tests, not Fast Mode, and OK.


Note: A comparison of the results with **Fast Mode** checked and unchecked, showed no difference in makeable contracts for a set of 36 boards, but I no longer check this box. The comprehensive tests check 6-card fits.

Computation of the makeable contracts will begin. It's probably time to deal the cards (see below). Just let the computation continue, no matter how long it takes.

Usually, I prepare a bunch of deals in advance, so that I can deal and print quickly.

Print Hand Record for Four H	lands
◎ Three across (18/page) ○ Four across (24/page)	
Header on Hand Record can have either of	two formats
 Format 1: Standard Header Standard format includes your name, Session Name, date(optional), and an optional 14 character large print entry in upper right corner. Enter optional text for large print in upper right corner of the Standard Header format (max. 14 characters) Handicap 	See Help File topic "Hand Record" for help.
• Format 2: Big Bold Unique Header Big Bold format will print as th <u>e header only</u> that which is entered in the "Big If you want the date to show, it must be in the Big Bold Heade Double click on the entry you want. Select "New" to create a new Big Bold I	er entry.
New Big Bold Header: Modify as required. To delete an entry, cl	ear it to all spaces.
Maximum size is about 60 characters of upper and lower case. U case unless your entry is very short. Heading will be left justified. spaces at the left and then use the following to see how well it is	se mostly lower To center it, insert
Test position on 8.5 x 11 paper Test position on A4 paper OK	per

- 10. When computation of the makeable contracts completes, this box will appear *be sure to get this right, there's no going back*:
 - a. Select **3 across (18/page)**, unless you are doing only 24 boards.
 - b. Select Format 1: Standard Header
 - c. Enter the type of game in the box under the Format 1 bullet, e.g. Handicap
 - d. Click OK.



11. Check the box for **Show Printer Dialog (enables entering Copy Count, etc.)**. In Europe, you probably want to check **A4 paper (not 8.5" x 11")**. Click **OK**.

Pr	inter		<u>? ×</u>
[Printer —		
	Name:	CutePDF Writer	
	Status:	Ready	
	Туре:	CutePDF Writer	
	Where:	CPW2:	
	Comment	:	
L			
	Network.		OK Cancel

12. Select **CutePDF Writer** as your printer, and click **OK**. Then click **OK** again on the following:

Pr	int				?×
[Printer				
	Name:	CutePDF Writer		~	Properties
	Status:	Ready			
	Type:	CutePDF Writer			
	Where:	CPW2:			
	Comment:				
[- Print range			Copies	
	● All			Number of c	opies: 1 🛨
	C Pages	from: 1	to: 9999		
	C Select	ion		1122	33 🗖 Collate
				OK	Cancel

Save in: 🗀 Temp	💌 🕂 🔁 (* 🎟 •
1 080325.pdf		
File name: 080401		Save
Save as type: PDF Files (*.pdf)	•	Cancel
Move up to CutePDF 3.0 and get advanced Easily edit PDF files, add security, stamps, bo booklets, impose (n-Up), split & merge PDFs,	ookmarks or header/foo	iter, make nuch more!

- 13. Save the PDF file to disk:
 - a. Name the resulting PDF file (YYMMDD or YYMMDDs, for consistency with ACBLscore)
 - b. Select the output directory (for example, C:\Temp)
 - c. Click Save



- 14. Click **NO**, do not print again.
- 15. Exit, Close Dealmaster Pro.

Deal the Cards

Pay attention to your posture to avoid repetitive strain or back injury!

I use flip-open boards. (If you don't have them, an assistant can definitely speed up the process, by removing cards from boards for you.) Here's my method of setting up the area for dealing:



1. Start the Dealer4 software.

👯 Main Mei	nu				- D ×
File Deal B	Edit Print :	Setup Main	tenance Help)	
New Load	ded	НСР	Distr	Hand Shapes	
Save Delete	Hand N			Shape Actual Ex	pected
Exit	E				
	s				
	w				
Inner Sir	nilarity:				
Min frequ	uency				
Max freq	luency				
	n Path Pty r 4 Ver 4.1				
History records	: 108				

2. Select File – Load.

Open De	al file					?×
	Look in:	🛅 dmpro		-	(= 🗈 💣 🗉	I •
My Re Docur Desi	nents	anguages 080325.DUP				
My Doc) uments					
My Cor	nputer					
My Ne	itwork _	File name: Files of type:	080401.DUP dup (*.dup)		•	Open Cancel
Plac	ces		Open as read-only		_	

3. Browse to where the deal file is (C:\dmpro), select the file, and click Open.

🚷 Main Menu					_ _ ×		
File Deal Edit Print Setup Maintenance Help							
Boards loaded	HCP	Distr	Hand Sh	apes			
36 Hand N	10.6	1.8	Shape	Actual	Expected 🔺		
	1		4432	31	31		
E	9.4	1.6	5332	16	22		
	1 3.4	1.0	5431	14	19		
s	10.0	1.7	5422	17	15		
	10.0	1.1	4333	14	15		
w			6322	9	8		
	9.9	1.8	6421	5	7		
	-		6331 5521	7	5		
Inner Similarity:	8	1:30	4441	10 7	5		
			7321	3	3		
Min frequency	8% 6♦	N	6430	2	2		
U			5440	1	2		
Max frequency	47% 9	P E	5530	2	1		
Migration Path Pty Ltd			6511	2	1		
Dealer 4 Ver 4.15.5			6520	0	1		
			7222	4	<u> </u>		
Ready							

1. Click **Deal**. Click **Deal** again on the next window:

👯 Dealing Progra	m		×
Data File:	C:\dmpro\080401.DUP		
Autodealer	Idle	Display Boards	;
	rd: 1 None er: North		
	W S	Ε	
Prev First	<u>N</u> ext <u>D</u> eal Last <u>B</u> reak		E <u>x</u> it

- Clear the area to the left and right of the monitor, push the keyboard and monitor back to allow 10+ inches (.25m), and set the PlayBridge Dealer4 machine back against the keyboard. Be sure it's connected to the computer and powered on. A good 60 inches (5 ft, 1.5m) of width is useful, with you in the center, in front of the machine, with an extra 4 inches (.1m) in front of that.
- 3. Connect the machine to power and the computer.
- 4. Check that the lens is clean. If not, use compressed air or a soft brush to clean it.
- 5. Get all 36 boards out and stack them up to your right, 12 to a stack, north pointed away from you, board 1 on top and nearest.
- 6. Remove the cards from the **last two boards** (35 & 36), and put them into the hopper, *face down*. This rotates the decks, so that they will wear evenly.
- 7. Remove the cards from board 1, and put them onto the hopper. They won't fit, but the extra weight will help.
- 8. Continuing for all boards:
 - a. Insert the open, empty board into the machine
 - b. Grab the next board, and put it on your lap, opening away from you
 - c. Remove the cards, two hands at a time, stacking them in front of the machine (to reduce wear on the joint, I don't open the board at this time)
 - d. Put the new cards onto the hopper
 - e. Look through the top if a card is leaning, push the top of the board down, and either poke the card down with a finger, or jiggle the aluminum flip plate until the card drops (see "The Flip Plate" below).
 - f. Remove the board from the machine, snap it securely closed, and stack it to the left, upside down make three stacks of 12 boards, neatly enough that they do not fall over.

The machine may have trouble with warped cards, especially if bowed up in the middle. Bend the cards down in the center, or hold them down lightly, if cards do not feed. While the last board is dealing, it helps to press down lightly on the middle of the deck with a finger nail.

Errors Detected by Dealer4 Software

After correcting any of these errors, you will usually have to click **Continue**, or press the **Start** button on the front left of the machine.

Card Recognition Error: The machine could not recognize a card. Check the bottom card (might be a Joker or upside down), the lens, and that there is sufficient weight on the hopper.

Card Feed Error: Usually, this means that the card on the bottom is not straight and flat, but it could indicate a card jam. Check the bottom card and the feed area.

No Card Box: The machine does not detect the presence of a bridge board, (or the flat dealing plate). Jiggle or press the board in firmly.

Lost Communication: Check both ends of the USB cable. Jiggle it or move to another port, if necessary.

The Flip Plate and Leaning Cards

The flip plate, on models designated "PlayBridgeDealer4" instead of just "Dealer4", is intended for use with flip-open boards. It generally improves the alignment of cards into the boxes of the board. However, it also contributes to the possibility of leaning cards.

The Dealer4 will not normally deal while the flip plate is raised, because card jams would result. You should be able to deal onto the flat plate with the flip plate in place, but you will have to raise the flip to remove the cards, and lower the flip for the next deal.

To remove the flip plate, from the designer's instructions:

- 1. Open the flip plate.
- 2. Using small pliers, remove the springs from both sides.
- 3. From the left side, remove the screw that is holding the flip plate in position.
- 4. Slide the flip plate off the right screw (it is not required to remove the right screw).
- 5. Be careful to save the plastic washers on both sides.
- 6. When the plate is removed, you cannot deal because software will issue a "Flip Plate Open" Error. To override it, first connect the machine to power and the computer. Click **Maintenance** on the Dealer4 software main menu. Check **Disable Flip Plate Switch**, and click on **Save Parameters**.

To reinstall the flip plate, reverse the above procedures. Dealing with the flip open (failing to reset the Maintenance option) will result in major card jams.

To reduce the likelihood of leaning cards, be sure the **card width adjustment** on the machine is not too tight (which could cause cards to twist, when dealt), and use sufficient pressure in the hopper, as recommended above. Clean cards should help.



My Dealer4 with spring-loaded aluminum "flip plate" and navy blue "new generation" bridge board in place. The Dealer4 software requires the flip plate to be down, whether dealing into a board or onto the plastic plate. Poke a finger through a hole or tap the side of the board to clear leaning cards.

For the first year with the Dealer4, I used Grimaud barcode cards that I got with with a Duplimate. At the end of that year, these cards had been used perhaps 60 times over two years. They still had some life in them, but being thicker and now slightly warped, they tended not to fall cleanly into the card boxes, as well as the occasional leaner. I replaced the Grimauds with ACBL cards, which are thinner: they rattle in the card boxes. Leaners are now very rare, and only an occasional shake or tap is needed to get the cards to nestle into the card boxes.

Final Check

When done dealing, remove the North hand from the next to last board (35) and check the spade suit against the hand records. This assures that the board set and hand records correspond, and that the cards were really dealt into the correct boards. (Early on, I had the hands and boards get out of sync a couple of times, especially when dealing onto the plate. The latest version of the Dealer4 software has eliminated this problem, but this check is easy.)

Examine and Print the Hand Records

Open the PDF file with Adobe Acrobat Reader, examine the results, and print as desired. If your printer will print two-sided automatically, then you probably don't need to know anything more.

If you have a 1-sided printer, open the paper tray (or feeder), take out a sheet of paper, write a word on it in pencil, put it back, and print something on it. Open the tray and use tape to label the inside to describe where the top of the page will print. This will come in handy for a number of applications.

Now, use this technique to print two-sided hand records:

- 1. Click on the displayed first page, just in case.
- 2. Click the Printer icon (File-Print).
- 3. Select **Current Page**, select the desired **number of copies**, and click **OK**.
- 4. Take the output, square the pages, and insert them into the paper tray, ready to print side two.
- 5. Scroll to the end of the file in Acrobat Reader, and **click on the second page**, just in case.
- 6. Click the Printer icon (File-Print).
- 7. Select Current Page, confirm the desired number of copies, and click OK.